Overview Package Class Tree Deprecated Index Help

Prev Class Next Class Frames No Frames All Classes

Summary: Nested | Field | Constr | Method Detail: Field | Constr | Method

com._604robotics.utils

Class VelocityController

java.lang.Object

com._604robotics.utils.VelocityController

public class VelocityController
extends Object

Class for controlling a motor's velocity, rather than its power directly. Uses a PID loop to scale to said velocity, and a distance-calibrated encoder for feedback.

Author:

Michael Smith, Kevin Parker

Constructor Summary

Constructors

Constructor and Description

VelocityController(double p, double i, double d, Encoder encoderLeft, Encoder encoderRight, RobotDrive robotDrive, Gyro gyro)

Initializes a new VelocityController.

Method Summary

Methods	
Modifier and Type	Method and Description
void	disable () Disables the VelocityController.
void	enable () Enables the VelocityController.
double	getActualVelocity() Gets the actual, current velocity.
double	getVelocity() Gets the current target velocity.
boolean	isEnabled() Is the VelocityController currently enabled?
void	<pre>setAngleGains (double pAngle, double iAngle, double dAngle) Based on gyro angles TODO - javadoc</pre>
void	setGains (double p, double i, double d) Reconfigures the gains on the PIDController.
void	setVelocity (double velocity) Sets the target velocity.

Methods inherited from class java.lang.Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, toString, wait, wait, wait

Constructor Detail

VelocityController

Initializes a new VelocityController.

Parameters:

- p The proportional term for the PIDController.
- ${\tt i}$ The integral term for the PIDController.
- d The derivative term for the PIDController.

encoder - The encoder to use for feedback.

output - The PIDOutput to control. Usually some sort of motor.

Method Detail

getVelocity

public double getVelocity()

Gets the current target velocity.

Returns:

The current target velocity.

getActualVelocity

public double getActualVelocity()

Gets the actual, current velocity.

Returns:

The actual, current velocity.

setVelocity

public void setVelocity(double velocity)

Sets the target velocity.

Parameters:

velocity - The target velocity to set.

setGains

Reconfigures the gains on the PIDController.

Parameters:

- $\ensuremath{\mathtt{p}}$ The proportional term for the PIDController.
- i The integral term for the PIDController.
- d The derivative term for the PIDController.

setAngleGains

Based on gyro angles TODO - javadoc

Parameters:

- p The
- i The
- d The

enable

public void enable()
Enables the VelocityController.

disable

public void disable()

Disables the VelocityController.

isEnabled

public boolean isEnabled()

Is the VelocityController currently enabled?

Returns

Whether or not the VelocityController is currently enabled.

