Overview Package Class Tree Deprecated Index Help

 Prev Class
 Next Class
 Frames
 No Frames
 All Classes

 Summary: Nested | Field | Constr | Method
 Detail: Field | Constr | Method

com._604robotics.utils

Class EncoderPIDSource

java.lang.Object
edu.wpi.first.wpilibj.SensorBase
edu.wpi.first.wpilibj.Encoder
com__604robotics.utils.EncoderOffset
com._604robotics.utils.EncoderPIDSource

All Implemented Interfaces:

CounterBase, IDevice, ISensor, PIDSource

public class EncoderPIDSource
extends EncoderOffset

Encoder extender that return the value of Encoder.get() when pidGet is called. Drop-in replacement: all constructors from the Encoder class are implemented here.

Author:

Michael Smith

Nested Class Summary

Nested classes/interfaces inherited from class edu.wpi.first.wpilibj.Encoder

Encoder.PIDSourceParameter

Nested classes/interfaces inherited from interface edu.wpi.first.wpilibj.CounterBase

CounterBase.EncodingType

Field Summary

Fields inherited from class edu.wpi.first.wpilibj.Encoder

m_aSource, m_bSource, m_indexSource

Fields inherited from class edu.wpi.first.wpilibj.SensorBase

 $k Analog Channels, \ k Analog Modules, \ k Digital Channels, \ k Pwm Channels, \ k Relay Channels, \ k Solenoid Channels, \ k Solenoid Modules, \ k System Clock Ticks Per Microsecond$

Constructor Summary

Constructors

Constructor and Description

EncoderPIDSource (DigitalSource aSource, DigitalSource bSource)

Encoder constructor.

EncoderPIDSource (DigitalSource aSource, DigitalSource bSource, boolean reverseDirection)

Encoder constructor.

EncoderPIDSource (DigitalSource aSource, DigitalSource bSource, boolean reverseDirection,

CounterBase.EncodingType encodingType)

Encoder constructor.

EncoderPIDSource (DigitalSource aSource, DigitalSource bSource, DigitalSource indexSource)

Encoder constructor.

EncoderPIDSource (DigitalSource aSource, DigitalSource bSource, DigitalSource indexSource, boolean reverseDirection)

Encoder constructor.

EncoderPIDSource(int aChannel, int bChannel)

Encoder constructor.

 ${\bf EncoderPIDSource} \mbox{(int aChannel, int bChannel, boolean reverse Direction)}$

Encoder constructor.

EncoderPIDSource(int aChannel, int bChannel, boolean reverseDirection, CounterBase.EncodingType encodingType)

EncoderPIDSource(int aChannel, int bChannel, int indexChannel)

Encoder constructor.

EncoderPIDSource (int aChannel, int bChannel, int indexChannel, boolean reverseDirection)

Encoder constructor

EncoderPIDSource(int aSlot, int aChannel, int bSlot, int bChannel)

Encoder constructor.

EncoderPIDSource (int aSlot, int aChannel, int bSlot, int bChannel, boolean reverseDirection)

Encoder constructor.

EncoderPIDSource(int aSlot, int aChannel, int bSlot, int bChannel, boolean reverseDirection,

CounterBase.EncodingType encodingType)

Encoder constructor.

EncoderPIDSource(int aSlot, int aChannel, int bSlot, int bChannel, int indexSlot, int indexChannel)

Encoder constructor.

EncoderPIDSource(int aSlot, int aChannel, int bSlot, int bChannel, int indexSlot, int indexChannel,

boolean reverseDirection)

Encoder constructor.

Method Summary

Methods

Modifier and Type Method and Description

double pidGet()

Hooks into the PIDSource interface

Methods inherited from class com. 604robotics.utils.EncoderOffset

getRaw, reset, setOffset

Methods inherited from class edu.wpi.first.wpilibj.Encoder

free, get, getDirection, getDistance, getPeriod, getRate, getStopped, setDistancePerPulse, setMaxPeriod, setMinRate, setPIDSourceParameter, setReverseDirection, start, stop

Methods inherited from class edu.wpi.first.wpilibj.SensorBase

checkAnalogChannel, checkAnalogModule, checkDigitalChannel, checkDigitalModule, checkPWMChannel, checkPWMModule, checkRelayChannel, checkRelayModule, checkSolenoidChannel, checkSolenoidModule, getDefaultAnalogModule, $\verb|getDefaultDigitalModule|, getDefaultSolenoidModule|, setDefaultAnalogModule|, setDefaultDigitalModule|, setDefaultDigi$ setDefaultSolenoidModule

Methods inherited from class java.lang.Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, toString, wait, wait, wait

Constructor Detail

EncoderPIDSource

public EncoderPIDSource(int aSlot,

int aChannel, int bSlot,

int bChannel,

boolean reverseDirection)

Encoder constructor. Construct a Encoder given a and b modules and channels fully specified.

Parameters:

aSlot - The a channel digital input module.

aChannel - The a channel digital input channel.

bSlot - The b channel digital input module.

 $\verb|bChanne| - The b channe| digital input channe|.$

reverseDirection - represents the orientation of the encoder and inverts the output values if necessary so forward represents positive values.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b modules and channels fully specified.

Parameters:

```
aSlot - The a channel digital input module.
```

aChannel - The a channel digital input channel.

bSlot - The b channel digital input module.

bChannel - The b channel digital input channel.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b modules and channels fully specified.

Parameters:

aSlot - The a channel digital input module.

aChannel - The a channel digital input channel.

bSlot - The b channel digital input module.

bChannel - The b channel digital input channel.

reverseDirection - represents the orientation of the encoder and inverts the output values if necessary so forward represents positive values.

encodingType - either k1X, k2X, or k4X to indicate 1X, 2X or 4X decoding. If 4X is selected, then an encoder FPGA object is used and the returned counts will be 4x the encoder spec'd value since all rising and falling edges are counted. If 1X or 2X are selected then a counter object will be used and the returned value will either exactly match the spec'd count or be double (2x) the spec'd count.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b modules and channels fully specified. Using the index pulse forces 4x encoding.

Parameters:

aSlot - The a channel digital input module.

aChannel - The a channel digital input channel.

bSlot - The b channel digital input module.

bChannel - The b channel digital input channel.

 $\verb|indexSlot- The index channel digital input module.|\\$

 $\verb|indexChanne|| \textbf{-} \textbf{The index channel digital input channel}.$

 $\verb|reverseDirection-represents| the orientation of the encoder and inverts the output values if necessary so forward represents positive values.$

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b modules and channels fully specified. Using the index pulse forces 4x encoding.

Parameters:

And the state of t

```
aStot - The a channel digital input module.
```

aChannel - The a channel digital input channel.

bSlot - The b channel digital input module.

bChannel - The b channel digital input channel.

indexSlot - The index channel digital input module.

indexChannel - The index channel digital input channel.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels assuming the default module.

Parameters:

aChannel - The a channel digital input channel.

bChannel - The b channel digital input channel.

reverseDirection - represents the orientation of the encoder and inverts the output values if necessary so forward represents positive values.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels assuming the default module.

Parameters:

aChannel - The a channel digital input channel.

bChannel - The b channel digital input channel.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels assuming the default module.

Parameters:

aChannel - The a channel digital input channel.

bChannel - The b channel digital input channel.

reverseDirection - represents the orientation of the encoder and inverts the output values if necessary so forward represents positive values.

encodingType - either k1X, k2X, or k4X to indicate 1X, 2X or 4X decoding. If 4X is selected, then an encoder FPGA object is used and the returned counts will be 4x the encoder spec'd value since all rising and falling edges are counted. If 1X or 2X are selected then a counter object will be used and the returned value will either exactly match the spec'd count or be double (2x) the spec'd count.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels assuming the default module. Using an index pulse forces 4x encoding

Parameters:

aChannel - The a channel digital input channel.

bChannel - The b channel digital input channel.

 $\verb|indexChanne|| \textbf{-} \textbf{The index channel digital input channel}.$

reverseDirection - represents the orientation of the encoder and inverts the output values if necessary so forward represents positive values.

EncoderPIDSource

```
int bChannel,
int indexChannel)
```

Encoder constructor. Construct a Encoder given a and b channels assuming the default module. Using an index pulse forces 4x encoding

Parameters:

aChannel - The a channel digital input channel.

bChannel - The b channel digital input channel.

 $\verb|indexChanne|| \textbf{-} \textbf{The index channel digital input channel}.$

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels as digital inputs. This is used in the case where the digital inputs are shared. The Encoder class will not allocate the digital inputs and assume that they already are counted.

Parameters:

aSource - The source that should be used for the a channel.

bSource - the source that should be used for the b channel.

reverseDirection - represents the orientation of the encoder and inverts the output values if necessary so forward represents positive values.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels as digital inputs. This is used in the case where the digital inputs are shared. The Encoder class will not allocate the digital inputs and assume that they already are counted.

Parameters:

aSource - The source that should be used for the a channel.

bSource - the source that should be used for the b channel.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels as digital inputs. This is used in the case where the digital inputs are shared. The Encoder class will not allocate the digital inputs and assume that they already are counted.

Parameters:

aSource - The source that should be used for the a channel.

bSource - the source that should be used for the b channel.

reverseDirection - represents the orientation of the encoder and inverts the output values if necessary so forward represents positive values.

encodingType - either k1X, k2X, or k4X to indicate 1X, 2X or 4X decoding. If 4X is selected, then an encoder FPGA object is used and the returned counts will be 4x the encoder spec'd value since all rising and falling edges are counted. If 1X or 2X are selected then a counter object will be used and the returned value will either exactly match the spec'd count or be double (2x) the spec'd count.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels as digital inputs. This is used in the case where the digital inputs are shared. The Encoder class will not allocate the digital inputs and assume that they already are counted.

Parameters:

aSource - The source that should be used for the a channel.

bSource - the source that should be used for the b channel.

indexSource - the source that should be used for the index channel.

reverseDirection - represents the orientation of the encoder and inverts the output values if necessary so forward represents positive values.

EncoderPIDSource

Encoder constructor. Construct a Encoder given a and b channels as digital inputs. This is used in the case where the digital inputs are shared. The Encoder class will not allocate the digital inputs and assume that they already are counted.

Parameters:

aSource - The source that should be used for the a channel.

bSource - the source that should be used for the b channel.

indexSource - the source that should be used for the index channel.

Method Detail

pidGet

public double pidGet()

Hooks into the PIDSource interface. This method overrides the one implemented by the underlying Encoder class, simply returning the value of this.get();

Specified by:

pidGet in interface PIDSource

Overrides:

pidGet in class Encoder

Returns:

The value to pass back to the PIDSource; in this case, that of this.get();

Overview Package Class Tree Deprecated Index Help

Prev Class Next Class Frames No Frames All Classes

Summary: Nested | Field | Constr | Method Detail: Field | Constr | Method